



# KODAK Image Access Enabling Software Version 2.0 Getting Started Guide

## ***Document Purpose***

Use this document to install the KODAK Image Access Enabling Software for DLS quickly and easily.

## ***KODAK Image Access Enabling Software Installation***

*Important: If a previous version of KODAK Image Access Enabling Software is already installed on your system, use the Add/Remove Program Utility from your WINDOWS Control Panel to remove it before continuing with this procedure.*

1. Install JRE 1.3.0 from the KODAK Image Access Enabling Software for DLS CD by double-clicking j2re1\_3\_0-win.exe.
2. Follow the instructions and complete the JRE installation.
3. Open the Disk1 folder from the KODAK Image Access Enabling Software for DLS Version 2.0 CD and double-click setup.exe to install the enabling software.

A message box displays saying the KODAK Image Access Enabling software installation is complete.

4. Restart the computer.

## ***Verify Enabling Software Installation***

Connect to the DLS Server with a Web browser. Use the URL [http://your\\_server\\_IP:8080/soap/servlet/rpcrouter](http://your_server_IP:8080/soap/servlet/rpcrouter) or <http://localhost:8080/soap/servlet/rpcrouter> if you are using a browser on the server. You should get back a page that says "Sorry, I don't speak via HTTP GET..."

## ***Remove KODAK Image Access Enabling Software***

Option 1: Use the Add/Remove Program Utility from your WINDOWS Control Panel to remove KODAK Image Access Enabling Software.

Option 2: Use the Setup.exe file.

1. Open the Disk1 folder from the KODAK Image Access Enabling Software for DLS Version 2.0 CD and double-click setup.exe to remove the enabling software.

A message box displays saying that the KODAK Image Access Enabling software is already installed.

2. Click **Yes** to remove the software.

A message box displays saying that the KODAK Image Access Enabling software has been removed.

3. Click **OK** to complete.